

Présentation détaillée

Sommaire

Organisation de la fonctionnalité
Génération des représentations visuelles de l'architecture
Arbre des royaumes
Vue détaillée de l'architecture globale
Vue détaillée par royaume
Génération des hôtes dans l'interface de Configuration

Il est possible via l'option `webui_log_users_enabled` d'activer des logs d'authentification supplémentaire dans un fichier spécifique. Cette option est configurable dans le fichier de configuration du module WebUI.



Pour plus d'information sur l'option `webui_log_users_enabled` voir la page de la configuration du module (voir la page [Configuration du module WebUI](#))

Log Externe d'Authentification

Authentification Réussi

Si `webui_log_users_add_user_name` est activé:

```
[ YYYY-MM-DD HH:MM:SS ] [ READ ] [ LOGIN ] [ RESULT:200 ] [ TIME: 1ms ] [ USER:<user_uid> /  
<user_name> ] [ CALL_BY:<IP> ] [ AUTHENTICATED:OK ] [ BY:UI Visualization ] [ AUTHENTICATED BY THE  
MODULE:<module_name> ]
```

Sinon:

```
[ YYYY-MM-DD HH:MM:SS ] [ READ ] [ LOGIN ] [ RESULT:200 ] [ TIME: 1ms ] [ USER:<user_uid> ] [  
CALL_BY:<IP> ] [ AUTHENTICATED:OK ] [ BY:UI Visualization ] [ AUTHENTICATED BY THE MODULE:<module_name>  
]
```

Authentification Échoué

Si `webui_log_users_add_user_name` est activé:

```
[ YYYY-MM-DD HH:MM:SS ] [ READ ] [ LOGIN ] [ RESULT:401 ] [ TIME: 4ms ] [ USER:<user_uid> /  
<user_name> ] [ CALL_BY:<IP> ] [ AUTHENTICATED:FAILED ] [ BY:UI Visualization ]
```

Sinon:

```
[ YYYY-MM-DD HH:MM:SS ] [ READ ] [ LOGIN ] [ RESULT:401 ] [ TIME: 4ms ] [ USER:<user_uid> ] [  
CALL_BY:<IP> ] [ AUTHENTICATED:FAILED ] [ BY:UI Visualization ]
```

Déconnexion

Si webui_log_users__add_user_name est activé:

```
[ YYYY-MM-DD HH:MM:SS ] [ READ ] [ LOGOUT ] [ RESULT:200 ] [ TIME: 0ms ] [ USER:<user_uid> /  
<user_name> ] [ CALL_BY:<IP> ] [ BY:UI Visualization ]
```

Sinon:

```
[ YYYY-MM-DD HH:MM:SS ] [ READ ] [ LOGOUT ] [ RESULT:200 ] [ TIME: 0ms ] [ USER:<user_uid> ] [  
CALL_BY:<IP> ] [ BY:UI Visualization ]
```