

Surcharge des paramètres du module (webui_cfg_overload.cfg)

Sommaire

[Description](#)

[Exemple : Surcharge de la configuration de l'interface Web](#)

Description

Le fichier de configuration des paramètres du module Webui pouvant être modifiés par les commandes Shinken, il est préférable d'ajuster les paramètres nécessaires dans le fichier suivant : **`/etc/shinken-user/configuration/daemons/brokers/modules/webui/webui_cfg_overload.cfg`**

Les paramètres définis dans ce fichier vont écraser ceux dans les fichiers de configuration des modules WebUI utilisant ce fichier.

Pour plus de détails sur les paramètres, référez vous à la page suivante : [Module WebUI](#)

Exemple : Surcharge de la configuration de l'interface Web

/etc/shinken-user/configuration/daemons/brokers/modules/webui/webui_cfg_overload.cfg

```
#*****
# This file contains overloaded values for webui configuration
# Example available in /etc/shinken-user-example/configuration/daemons/brokers/modules/webui
/webui_cfg_overload.cfg
#*****

#=====
#===== default_tiles_format =====

                                # Describe how the tiles are displayed in the hive.
                                #
                                # Possible values:
                                #
                                # - context : (default) Tile is of the color of the
context when there is one, else of the status.
                                #
                                # - context_and_status : Tile color is split
between status and context, when there is one.
                                #
                                # - status : Tile is always of the color of the
status. Context is displayed as a secondary icon.
tiles_background=context_and_status
#=====
#===== Colors for graphics =====

                                # Give the list of color format hexadecimal (without
the #) separate by comma
                                #
                                # Possible values ==> any existing color
                                # size => infinite

colors_graphics=6cc4b9,4485aa,314293,329347,72a82c,ef7c14,d82e2e,931616,FF00FF,000000
#=====

#===== Webui Authentication External Log =====

                                # Log the webui authentication history in a file

                                # Enable authentication log or not.
                                # by default: 0 (disabled)

webui_log_users_enabled=0

                                # File use for log authentication history

webui_log_users_file_path=/var/log/shinken/webui/log_users.log

                                # Add user name to log.
                                # by default: 0 (disabled)

webui_log_users_add_user_name=0
```