

# Receiver - receiver--module-last-configuration-recorder - Exemple de log

```
[2024-09-26 10:29:54] INFO : [ receiver-master ] Modules directory: /opt/shinken/modules
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [
directory=receiver_module_generic_endpoint ] Starting to load the module code from directory /opt/shinken
/modules/receiver_module_generic_endpoint.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [
directory=receiver_module_generic_endpoint ] Try to import code from /opt/shinken/modules
/receiver_module_generic_endpoint as python module.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [
directory=receiver_module_generic_endpoint ] Successfully imported the directory /opt/shinken/modules
/receiver_module_generic_endpoint as a python module.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [
directory=receiver_module_generic_endpoint ] Loading the module source file /opt/shinken/modules
/receiver_module_generic_endpoint/module.py.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [ directory=named_pipe
] Starting to load the module code from directory /opt/shinken/modules/named_pipe.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [ directory=named_pipe
] Try to import code from /opt/shinken/modules/named_pipe as python module.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [ directory=named_pipe
] Successfully imported the directory /opt/shinken/modules/named_pipe as a python module.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [ directory=named_pipe
] Loading the module source file /opt/shinken/modules/named_pipe/module.py.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [ directory=ws_arbiter
] Starting to load the module code from directory /opt/shinken/modules/ws_arbiter.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [ directory=ws_arbiter
] Try to import code from /opt/shinken/modules/ws_arbiter as python module.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [ directory=ws_arbiter
] Successfully imported the directory /opt/shinken/modules/ws_arbiter as a python module.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [ directory=ws_arbiter
] Loading the module source file /opt/shinken/modules/ws_arbiter/module.py.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [
directory=last_configuration_recorder ] Starting to load the module code from directory /opt/shinken/modules
/last_configuration_recorder.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [
directory=last_configuration_recorder ] Try to import code from /opt/shinken/modules
/last_configuration_recorder as python module.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [
directory=last_configuration_recorder ] Successfully imported the directory /opt/shinken/modules
/last_configuration_recorder as a python module.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] [
directory=last_configuration_recorder ] Loading the module source file /opt/shinken/modules
/last_configuration_recorder/module.py.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CODE-LOADING ] A total of 4 Shinken
Enterprise modules are available for this daemon/module ( receiver ): receiver-module-generic-endpoint, named-
pipe, ws-arbiter, receiver--module-last-configuration-recorder ( on a total of 41, loaded in 0.090s )
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CREATION ] [ receiver--module-last-
configuration-recorder--shinken-receiver-master ] [ module-type=receiver__module_last_configuration_recorder ]
[0.002s] The module is created.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CREATION ] [ receiver--module-last-
configuration-recorder--shinken-receiver-master ] [ module-type=receiver__module_last_configuration_recorder ]
Trying to init module.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ receiver--module-last-configuration-recorder--shinken-
receiver-master ] [ INITIALISATION ] - receiver__module_last_configuration_recorder__daemon_id —— : 0
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ receiver--module-last-configuration-recorder--shinken-
receiver-master ] [ INITIALISATION ] - receiver__module_last_configuration_recorder__daemon_type - :
receiver
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ receiver--module-last-configuration-recorder--shinken-
receiver-master ] [ INITIALISATION ] - receiver__module_last_configuration_recorder__directory —— : /var/lib
/shinken/persistent_data/last_configuration_recorder/daemons
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ receiver--module-last-configuration-recorder--shinken-
receiver-master ] [ INITIALISATION ] - receiver__module_last_configuration_recorder__enable —— : 1
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ CREATION ] [ receiver--module-last-
configuration-recorder--shinken-receiver-master ] [ module-type=receiver__module_last_configuration_recorder ]
The module is started.
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ receiver--module-last-configuration-recorder--shinken-
receiver-master ] [ CONFIGURATION ] [ LOADER ] loading inventories from file [ /var/lib/shinken/persistent_data
```

```
/last_configuration_recorder/daemons/receiver/0/inventories ] for daemon shinken-receiver-master
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ INVENTORY ] The realm All inventory is now updated
with 40 elements and the hash 06b98605ec25a3dfd486e8946349c50065f35fb8
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ receiver--module-last-configuration-recorder--shinken-
receiver-master ] [ CONFIGURATION ] [ LOADER ] loading host mapping from file [ /var/lib/shinken/persistent_data
/last_configuration_recorder/daemons/receiver/0/host-mapping ] for daemon shinken-receiver-master
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ HOSTS TO SCHEDULER MAPPING ] HOSTNAME<->SCHEDULER-SHARD
mapping: scheduler with 1 shard_id
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ receiver--module-last-configuration-recorder--shinken-
receiver-master ] [ CONFIGURATION ] [ LOADER ] loading configuration from file [ /var/lib/shinken
/persistent_data/last_configuration_recorder/daemons/receiver/0/configuration ] for daemon shinken-receiver-
master
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ CONFIGURATION ] [ RETENTION ] Loaded from retention (
Architecture=Shinken-Production name=arbiter-master spare=False expiration=180s) ( MASTER arbiter server
uid=f52f1c69-f9cf-45ad-ae8d-1c05bcf533bf )
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ CONFIGURATION ] ----- Loading the new configuration from
retention
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ CONFIGURATION ] New configuration loaded from retention:
[configuration_uuid=9f79910034684107b8c37e29fae6d442, arbiter=arbiter-master, architecture=Shinken-Production,
date=25-09-2024 19:20:38]
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ CONFIGURATION ] Switching from not direct routing to
direct routing: ON
[2024-09-26 10:29:54] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ UPDATE ] No modules have changed

[2024-09-26 10:30:06] INFO : [ receiver-master ] [ INVENTORY ] inventories are up to date, updating
realms configuration uuid from 9f79910034684107b8c37e29fae6d442 to 5aa3d8a5cfa74cc59f04f9b43
[2024-09-26 10:30:06] INFO : [ receiver-master ] [ receiver--module-last-configuration-recorder--shinken-
receiver-master ] [ CONFIGURATION ] [ RECORDER ] Saving inventories to file [ /var/lib/shinken/persistent_data
/last_configuration_recorder/daemons/receiver/0/inventories ] for daemon shinken-receiver-master
[2024-09-26 10:30:06] INFO : [ receiver-master ] [ receiver--module-last-configuration-recorder--shinken-
receiver-master ] [ CONFIGURATION ] [ RECORDER ] Saving configuration to file [ /var/lib/shinken/persistent_data
/last_configuration_recorder/daemons/receiver/0/configuration ] for daemon shinken-receiver-master
[2024-09-26 10:30:07] INFO : [ receiver-master ] [ CONFIGURATION ] [ UPDATE ] ----- Loading a configuration
update from the arbiter
[2024-09-26 10:30:07] INFO : [ receiver-master ] [ CONFIGURATION ] [ UPDATE ] The arbiter has sent us a new
configuration: [configuration_uuid=5aa3d8a5cfa74cc59f04f9b43, arbiter=arbiter-master,
architecture=Shinken-Production, date=26-09-2024 10:30:02]
[2024-09-26 10:30:07] INFO : [ receiver-master ] [ MODULES-MANAGER ] [ UPDATE ] No modules have changed
[2024-09-26 10:30:08] INFO : [ receiver-master ] [ HOSTS TO SCHEDULER MAPPING ] HOSTNAME<->SCHEDULER-SHARD
mapping: scheduler with 1 shard_id
[2024-09-26 10:30:08] INFO : [ receiver-master ] [ receiver--module-last-configuration-recorder--shinken-
receiver-master ] [ CONFIGURATION ] [ RECORDER ] Saving host mapping to file [ /var/lib/shinken/persistent_data
/last_configuration_recorder/daemons/receiver/0/host-mapping ] for daemon shinken-receiver-master
```